

## Storage Modes

This chapter explains the Storage modes.

### Note:

To use Plantview Storage you first need to set up Storage in the Administration section (Guide 13).

### Contents

1. Storage modes .....	1
2. Simple Storage mode (S) .....	2
2.1 Publish .....	2
2.2 Upload the project folder .....	3
2.3 Download the project folder .....	3
2.4 Upload/Download Status .....	3
3. Advanced Storage mode (A) .....	4
3.1 Publish .....	5
3.2 Upload the project folder .....	5
3.3 Download the project folder .....	6
3.4 Upload/Download Status .....	7


### Use Plantview Workspace

#### 1. Storage modes

Plantview is equipped with two modes to manage upload and download of the data between Storage and your Workspace.

- **Simple Storage mode (S)** is a simplified interface intended for the beginner user with automated functionality.
- **Advanced Storage mode (A)** is an advanced interface for the advanced user that provides additional functionality.


Plantview initially starts in Simple Storage mode (S).



## 2. Simple Storage mode (S)

Following is an overview of the functionality presented with Simple Storage mode.

The **S** symbol indicates the active Storage mode




### 2.1 Publish

Publish offers the **Full Publish** option. The **Full Publish** will perform two operations.


- 1 Publish the project structure to the Administration Server
- 2 Perform a Smart Upload

**Smart Upload** checks for new and changed files and will only Upload files if needed.



## 2.2 Upload the project folder


Storage/Upload Data will perform a Smart Upload 2



## 2.3 Download the project folder

Storage/Download Data will perform a Smart Download 2


Smart Download checks for new and changed files and will only Download files if needed.



## 2.4 Upload/Download Status

To update the Upload/Download Status press **Refresh**

Press on the running status button and press on **Downloading/Uploading** to enter the TRANSFER STATE tab



The TRANSFER STATE window opens where you can view the Status of the Upload/Download

**Download state** Navigate

Download Apartment 2

State	Start	End	
done	5 Aug 2022 18:28:30	5 Aug 2022 18:46:14	17'44"

**Transfer queue** 0

Transfer queue is empty

**Files transferred** 38 (14.23 GB)

**recap** 13 (11.70 GB)

Job ID	Status	Size	Date	Time
Job 005- s012	downloaded	588.48 MB	5 Aug 2022	01'40"
Job 005- s011	downloaded	517.46 MB	5 Aug 2022	01'29"
Job 005- s010	downloaded	529.46 MB	5 Aug 2022	01'33"
Job 005- s009	downloaded	497.07 MB	5 Aug 2022	01'30"
Job 005- s008	downloaded	430.30 MB	5 Aug 2022	01'16"
Job 005- s007	downloaded	467.70 MB	5 Aug 2022	01'23"
Job 005- s006	downloaded	477.79 MB	5 Aug 2022	01'23"

**Transfers failed** 0

No failures exist

### 3. Advanced Storage mode (A)

To switch from Simple Storage Mode (S) to Advanced Storage Mode (A) press on the mode symbol

Username: zeppos Account: VIIN GmbH Communication code: Qlajo Assign

Apartment 2

**Project**

Apartment 2  
apartment\_2-2022.01.07-10.57.22

Showing 1 to 1 of 1 entries (filtered from 134 total)

Storage mode

Storage mode is set to Simple

Confirm to enable the **Advanced Storage mode**

Confirm Cancel

Following is an overview of the functionality presented with Advanced Storage mode.

### 3.1 Publish


Publish offers two options, **Full Publish** and **Publish**

**Full publish** will perform two operations.

- 1 Publish the project structure to the Administration Server
- 2 Perform a Smart Upload


**Publish** will perform one operation.

- 1 Publish the project structure to the Administration Server




### 3.2 Upload the project folder

Press on **Storage/Upload Data**



**Storage/Upload Data** will open the **UPLOAD DATA** section



The **UPLOAD DATA** Section offers extended functionality to define the upload:


- Individually Select items to upload
- Filter the elements shown for easier selection

The Upload button offers two options, **Smart Upload** and **Upload**


- Upload will force upload all selected elements. 2
- Smart Upload checks for new and changed files and will only Upload files if needed. 2

### 3.3 Download the project folder

Press on **Storage/Download Data**



**Storage/Upload Data** will open the **UPLOAD DATA** section



The **DOWNLOAD DATA** Section offers extended functionality to define the download:

- Individually Select items to download
- Filter the elements shown for easier selection

The **Download** button offers two options, **Smart Download** and **Download**

- Download will force download all selected elements. 2
- Smart Download checks for new and changed files and will only Download files if needed. 2

### 3.4 Upload/Download Status

The **TRANSFER STATE** window opens where you can view the Status of the Upload/Download

